

Converting CSV to DAT – For Import into Personal Data

Introduction:

The following are the instructions on the layout required to convert a CSV file into a DAT file for purpose of importing demographic information into Parklane. For full instructions on the Data Transfer, consult the Data Transfer Guide.


File Requirements:

The following criteria must be met to successfully convert a file:

- 1. The file must be a comma separated value (CSV) file (this can be creating using Excel)
- 2. If importing Badge ID into Personal Data, and it is above 11 characters, this field must be text formatted.
- 3. For those with multiple companies, one file must be created for each company.
- 4. The first line can have headings, but if so, the Lastname field must contain, "Lastname", and then the header will be skipped. OR, delete header before converting.
- 5. Click here for a CSV file with headings.

Instructions to convert Excel file to CSV

- Once data is populated and formatted in the Excel file according to the layout, select <u>File</u>, then <u>Save As</u>
- 2. Under Save as type, select: CSV (comma delimited)(*.csv) see image below



- 3. Once complete, go to Maintenance, select Data Transfer > Convert CSV to DAT
- 4. When File Upload panel appears, select F2 to search and select CSV file
- 5. System will prompt: Ready to Run File Conversion? Select Yes.
- 6. When complete, select OK.



- 7. System will place the converted file, now named ParklaneCSV.DAT in the appropriate system folder (HS)
- 8. IMPORTANT: Run the Data Transfer as outlined in the <u>Data Transfer Guide</u> First, <u>be sure</u> to do a <u>Trial Run before</u> updating.
- 9. When running, you can access the ParklaneCSV.DAT file by changing name of file in field to ParklaneCSV.DAT, then Continue.



10. Should you require assistance, contact Parklane Support.



Column to <u>Data Transfer Layout</u> field reference. For sample CSV with headings <u>click here</u>.

Column	Data Transfer Layout Field								
Α	1	Q	17	AG	33	AW	49	BM	65
В	2	R	18	АН	34	AX	50	BN	66
С	3	S	19	Al	35	AY	51	во	67
D	4	Т	20	AJ	36	AZ	52	BP	68
Е	5	U	21	AK	37	BA	53	BQ	69
F	6	٧	22	AL	38	BB	54	BR	70
G	7	W	23	AM	39	ВС	55	BS	71
Н	8	X	24	AN	40	BD	56	ВТ	72
1	9	Υ	25	AO	41	BE	57		
J	10	Z	26	AP	42	BF	58		
K	11	AA	27	AQ	43	BG	59		
L	12	AB	28	AR	44	ВН	60		
М	13	AC	29	AS	45	ВІ	61		
N	14	AD	30	AT	46	BJ	62		
0	15	AE	31	AU	47	BK	63		
Р	16	AF	32	AV	48	BL	64		·